




Using Odysseyware with Internet Explorer


Odysseyware is fully supported under Internet Explorer 8 and higher. This document details the browser settings that we find work best with the program, allowing Internet Explorer users to get the best experience.

Multimedia Rendering Odysseyware uses Adobe Flash to render videos, games, audio cues and other multimedia elements. We recommend installing Adobe Flash on all user workstations, and being sure to keep it up to date. You can learn more about Adobe Flash and acquire the installation files at the following website: <http://www.adobe.com/software/flash/about/>


PDF Reader Odysseyware often presents information such as reports and supplementary items to the user as a PDF file. We recommend installing the latest version of Adobe Acrobat Reader on all user workstations, and being sure to keep it up to date. You can acquire the free download of Adobe Acrobat Reader at the following website: <http://get.adobe.com/reader/>


Page Rendering All workstation browsers should have Javascript enabled in order to ensure that Odysseware's pages and navigation links are properly rendered. In Internet Explorer 8 and above, you can check Javascript by following these steps:

1. In the Internet Explorer menu bar, click on Tools, then select Internet Options. If your menu bar is disabled, click the gear-shaped Tools icon , then Internet Options.
2. In the Internet Options dialogue, choose the Security tab.
3. Next, select Custom Level.
4. In the Scripting section, be sure that Active Scripting is enabled.





Password Saving To keep your users' passwords secure, we recommend disabling Internet Explorer's password save feature. This will prevent users from accidentally saving their Odysseyware password, allowing unauthorized access to their account. To disable this feature in Internet Explorer 8 and above, please follow these steps:

1. In the Internet Explorer menu bar, click on Tools, then select Internet Options. If your menu bar is disabled, click the gear-shaped Tools icon , then Internet Options.
2. In the Internet Options dialogue, choose the Content tab.
3. Under the AutoComplete section, click the Settings button.
4. Next, uncheck the option for User Names and Passwords on Forms. IE will no longer attempt to store usernames and passwords.




AutoComplete AutoComplete can be confusing for students who may mistake the list of form suggestions for a list of answers they need to choose from. We recommend turning AutoComplete for forms off in Internet Explorer, following the steps below:

1. In the Internet Explorer menu bar, click on Tools, then select Internet Options. If your menu bar is disabled, click the gear-shaped Tools icon , then Internet Options.
2. In the Internet Options dialogue, choose the Content tab.
3. Under the AutoComplete section, click the Settings button.
4. Next, uncheck the option for Forms.



Caching Options We recommend that workstation browsers be set up to clear the cache each time they are closed. You can enable this feature in Internet Explorer by following the steps below:

1. In the Internet Explorer menu bar, click on Tools, then select Internet Options. If your menu bar is disabled, click the gear-shaped Tools icon , then Internet Options.
2. In the Internet Options dialogue, choose the Advanced tab.
3. Scroll down to the Security section, and place a check mark next to Empty Temporary Internet Files Folder When the Browser is Closed.

